

Table of Contents

<u>IP Addressing and Subnetting for New Users</u>	1
<u>Document ID: 13788</u>	1
<u>Introduction</u>	1
<u>Prerequisites</u>	1
<u>Requirements</u>	1
<u>Components Used</u>	1
<u>Additional Information</u>	1
<u>Conventions</u>	2
<u>Understanding IP Addresses</u>	2
<u>Network Masks</u>	3
<u>Understanding Subnetting</u>	4
<u>Examples</u>	5
<u>Sample Exercise 1</u>	6
<u>Sample Exercise 2</u>	6
<u>VLSM Example</u>	7
<u>VLSM Example</u>	8
<u>CIDR</u>	9
<u>Appendix</u>	9
<u>Sample Config</u>	9
<u>Host/Subnet Quantities Table</u>	10
<u>NetPro Discussion Forums – Featured Conversations</u>	11
<u>Related Information</u>	11

IP Addressing and Subnetting for New Users

Document ID: 13788

Introduction

Prerequisites

- Requirements
- Components Used
- Additional Information
- Conventions

Understanding IP Addresses

Network Masks

Understanding Subnetting

Examples

- Sample Exercise 1
- Sample Exercise 2

VLSM Example

- VLSM Example

CIDR

Appendix

- Sample Config
- Host/Subnet Quantities Table

NetPro Discussion Forums – Featured Conversations

Related Information

Introduction

This document will give you basic information you will need to configure your router for routing IP, such as how addresses are broken down and how subnetting works. You will learn how to assign each interface on the router an IP address with a unique subnet. And do not worry, we will show you lots of examples to help tie everything together.

Prerequisites

Requirements

There are no specific prerequisites for this document.

Components Used

This document is not restricted to specific software and hardware versions.

Additional Information

If definitions are helpful to you, use these vocabulary terms to get you started:

- **Address** The unique number ID assigned to one host or interface in a network.
- **Subnet** A portion of a network sharing a particular subnet address.

- **Subnet mask** A 32-bit combination used to describe which portion of an address refers to the subnet and which part refers to the host.
- **Interface** A network connection.

If you have already received your legitimate address(es) from the InterNIC (Internet Network Information Center), you are ready to begin. If you are not planning on connecting to the Internet, we strongly suggest that you use reserved addresses from RFC 1918 .

Conventions

For more information on document conventions, see the Cisco Technical Tips Conventions.

Understanding IP Addresses

An IP address is an address used to uniquely identify a device on an IP network. The address is made up of 32 binary bits which can be divisible into a network portion and host portion with the help of a subnet mask. The 32 binary bits are broken into four octets (1 octet = 8 bits). Each octet is converted to decimal and separated by a period (dot). For this reason, an IP address is said to be expressed in dotted decimal format (for example, 172.16.81.100). The value in each octet ranges from 0 to 255 decimal, or 00000000 – 11111111 binary.

Here is how binary octets convert to decimal: The right most bit, or least significant bit, of an octet will hold a value of 2^0 . The bit just to the left of that will hold a value of 2^1 . This continues until the left-most bit, or most significant bit, which will hold a value of 2^7 . So if all binary bits are a one, the decimal equivalent would be 255 as shown here:

```

1 1 1 1 1 1 1 1
128 64 32 16 8 4 2 1 (128+64+32+16+8+4+2+1=255)

```

Here is a sample octet conversion when not all of the bits are set to 1.

```

0 1 0 0 0 0 0 1
0 64 0 0 0 0 0 1 (0+64+0+0+0+0+0+1=65)

```

And this is sample shows an IP address represented in both binary and decimal.

```

10. 1. 23. 19 (decimal)
00001010.00000001.00010111.00010011 (binary)


```

These octets are broken down to provide an addressing scheme that can accommodate large and small networks. There are five different classes of networks, A to E. This document focuses on addressing classes A to C, since classes D and E are reserved and discussion of them is beyond the scope of this document.

Note: Also note that the terms "Class A, Class B" and so on are used in this document to help facilitate the understanding of IP addressing and subnetting. These terms are rarely used in the industry anymore because of the introduction of classless interdomain routing (CIDR).

Given an IP address, its class can be determined from the three high-order bits. Figure 1 shows the significance in the three high order bits and the range of addresses that fall into each class. For informational purposes, Class D and Class E addresses are also shown.

Figure 1



In a Class A address, the first octet is the network portion, so the Class A example in Figure 1 has a major network address of 10. Octets 2, 3, and 4 (the next 24 bits) are for the network manager to divide into subnets and hosts as he/she sees fit. Class A addresses are used for networks that have more than 65,536 hosts (actually, up to 16,777,214 hosts!).

In a Class B address, the first two octets are the network portion, so the Class B example in Figure 1 has a major network address of 172.16. Octets 3 and 4 (16 bits) are for local subnets and hosts. Class B addresses are used for networks that have between 256 and 65,534 hosts.

In a Class C address, the first three octets are the network portion. The Class C example in Figure 1 has a major network address of 193.18.9. Octet 4 (8 bits) is for local subnets and hosts – perfect for networks with less than 254 hosts.

Network Masks


A network mask helps you know which portion of the address identifies the network and which portion of the address identifies the node. Class A, B, and C networks have default masks, also known as natural masks, as shown here:

```
Class A: 255.0.0.0
Class B: 255.255.0.0
Class C: 255.255.255.0
```

An IP address on a Class A network that has not been subnetted would have an address/mask pair similar to: 8.20.15.1 255.0.0.0. To see how the mask helps you identify the network and node parts of the address, convert the address and mask to binary numbers.

```
8.20.15.1 = 00001000.00010100.00001111.00000001
255.0.0.0 = 11111111.00000000.00000000.00000000
```


Figure 2



Notice that each of the routers in Figure 2 is attached to four subnetworks, one subnetwork is common to both routers. Also, each router has an IP address for each subnetwork to which it is attached. Each subnetwork could potentially support up to 30 host addresses.

This brings up an interesting point. The more host bits you use for a subnet mask, the more subnets you have available. However, the more subnets available, the less host addresses available per subnet. For example, a Class C network of 204.17.5.0 and a mask of 255.255.255.224 (/27) allows you to have eight subnets, each with 32 host addresses (30 of which could be assigned to devices). If you use a mask of 255.255.255.240 (/28), the break down is:

```

204.17.5.0 - 11001100.00001111.00000101.00000000
255.255.255.240 - 11111111.11111111.11111111.11110000
                    -----|sub|-----
  
```

Since you now have four bits to make subnets with, you only have four bits left for host addresses. So in this case you can have up to 16 subnets, each of which can have up to 16 host addresses (14 of which can be assigned to devices).

Take a look at how a Class B network might be subnetted. If you have network 172.16.0.0, then you know that its natural mask is 255.255.0.0 or 172.16.0.0/16. Extending the mask to anything beyond 255.255.0.0 means you are subnetting. You can quickly see that you have the ability to create a lot more subnets than with the Class C network. If you use a mask of 255.255.248.0 (/21), how many subnets and hosts per subnet does this allow for?

```

172.16.0.0 - 10101100.00010000.00000000.00000000
255.255.248.0 - 11111111.11111111.11111000.00000000
                    -----|sub|-----
  
```

You are using five bits from the original host bits for subnets. This will allow you to have 32 subnets (2^5). After using the five bits for subnetting, you are left with 11 bits for host addresses. This will allow each subnet so have 2048 host addresses (2^{11}), 2046 of which could be assigned to devices.

Note: In the past, there were limitations to the use of a subnet 0 (all subnet bits are set to zero) and all ones subnet (all subnet bits set to one). Some devices would not allow the use of these subnets. Cisco Systems devices will allow the use of these subnets when their **subnet zero** command is configured.

Examples

Sample Exercise 1

Now that you have an understanding of subnetting, put this knowledge to use. In this example, you are given two address / mask combinations, written with the prefix/length notation, which have been assigned to two devices. Your task is to determine if these devices are on the same subnet or different subnets. You can do this by using the address and mask of each device to determine to which subnet each address belongs.

```
DeviceA: 172.16.17.30/20
DeviceB: 172.16.28.15/20
```

Determining the Subnet for DeviceA:

```
172.16.17.30 - 10101100.00010000.00010001.00011110
255.255.240.0 - 11111111.11111111.11110000.00000000
-----| sub|-----
subnet =      10101100.00010000.00010000.00000000 = 172.16.16.0
```

Looking at the address bits that have a corresponding mask bit set to one, and setting all the other address bits to zero (this is equivalent to performing a logical "AND" between the mask and address), shows you to which subnet this address belongs. In this case, DeviceA belongs to subnet 172.16.16.0.

Determining the Subnet for DeviceB:


```
172.16.28.15 - 10101100.00010000.00011100.00001111
255.255.240.0 - 11111111.11111111.11110000.00000000
-----| sub|-----
subnet =      10101100.00010000.00010000.00000000 = 172.16.16.0
```

From these determinations, DeviceA and DeviceB have addresses that are part of the same subnet.

Sample Exercise 2

Given the Class C network of 204.15.5.0/24, subnet the network in order to create the network in Figure 3 with the host requirements shown.

Figure 3



Looking at the network shown in Figure 3, you can see that you are required to create five subnets. The largest subnet must support 28 host addresses. Is this possible with a Class C network? and if so, then how?

You can start by looking at the subnet requirement. In order to create the five needed subnets you would need to use three bits from the Class C host bits. Two bits would only allow you four subnets (2^2).

Since you need three subnet bits, that leaves you with five bits for the host portion of the address. How many

hosts will this support? $2^5 = 32$ (30 usable). This meets the requirement.

Therefore you have determined that it is possible to create this network with a Class C network. An example of how you might assign the subnetworks is:

netA: 204.15.5.0/27	host address range 1 to 30
netB: 204.15.5.32/27	host address range 33 to 62
netC: 204.15.5.64/27	host address range 65 to 94
netD: 204.15.5.96/27	host address range 97 to 126
netE: 204.15.5.128/27	host address range 129 to 158

VLSM Example

In all of the previous examples of subnetting you will notice that the same subnet mask was applied for all the subnets. This means that each subnet has the same number of available host addresses. You may need this in some cases, but, in most cases, having the same subnet mask for all subnets ends up wasting address space. For example, in the Sample Exercise 2 section, a class C network was split into eight equal-size subnets; however, each subnet did not utilize all available host addresses, which results in wasted address space. Figure 4 illustrates this wasted address space.

Figure 4




Figure 4 illustrates that of the subnets that are being used, NetA, NetC, and NetD have a lot of unused host address space. This may have been a deliberate design accounting for future growth, but in many cases this is just wasted address space due to the fact that the same subnet mask is being used for all the subnets.

Variable Length Subnet Masks (VLSM) allows you to use different masks for each subnet, thereby using address space efficiently.

VLSM Example

Given the same network and requirements as in Sample Exercise 2 develop a subnetting scheme using VLSM, given:

```
netA: must support 14 hosts
netB: must support 28 hosts
netC: must support 2 hosts
netD: must support 7 hosts
netE: must support 28 host
```

Determine what mask allows the required number of hosts.

```
netA: requires a /28 (255.255.255.240) mask to support 14 hosts
netB: requires a /27 (255.255.255.224) mask to support 28 hosts
netC: requires a /30 (255.255.255.252) mask to support 2 hosts
netD*: requires a /28 (255.255.255.240) mask to support 7 hosts
netE: requires a /27 (255.255.255.224) mask to support 28 hosts
```

```
* a /29 (255.255.255.248) would only allow 6 usable host addresses
therefore netD requires a /28 mask.
```

The easiest way to assign the subnets is to assign the largest first. For example, you can assign in this manner:

```
netB: 204.15.5.0/27 host address range 1 to 30
netE: 204.15.5.32/27 host address range 33 to 62
netA: 204.15.5.64/28 host address range 65 to 78
netD: 204.15.5.80/28 host address range 81 to 94
netC: 204.15.5.96/30 host address range 97 to 98
```

This can be graphically represented as shown in Figure 5:

Figure 5




Figure 5 illustrates how using VLSM helped save more than half of the address space.

CIDR

Classless Interdomain Routing (CIDR) was introduced to improve both address space utilization and routing scalability in the Internet. It was needed because of the rapid growth of the Internet and growth of the IP routing tables held in the Internet routers.

CIDR moves away from the traditional IP classes (Class A, Class B, Class C, and so on). In CIDR, an IP network is represented by a prefix, which is an IP address and some indication of the length of the mask. Length means the number of left-most contiguous mask bits that are set to one. So network 172.16.0.0 255.255.0.0 can be represented as 172.16.0.0/16. CIDR also depicts a more hierarchical Internet architecture, where each domain takes its IP addresses from a higher level. This allows for the summarization of the domains to be done at the higher level. For example, if an ISP owns network 172.16.0.0/16, then the ISP can offer 172.16.1.0/24, 172.16.2.0/24, and so on to customers. Yet, when advertising to other providers, the ISP only needs to advertise 172.16.0.0/16.

For more information on CIDR, see RFC 1518 and RFC 1519.

Appendix

Sample Config

Routers A and B are connected via serial interface.

Router A

```
hostname routera
!
ip routing
!
int e 0
ip address 172.16.50.1 255.255.255.0
!(subnet 50)
int e 1 ip address 172.16.55.1 255.255.255.0
!(subnet 55)
int t 0 ip address 172.16.60.1 255.255.255.0
!(subnet 60) int s 0
ip address 172.16.65.1 255.255.255.0 (subnet 65)
!S 0 connects to router B
router rip
network 172.16.0.0
```

Router B

```
hostname routerb
!
ip routing
!
int e 0
ip address 192.1.10.200 255.255.255.240
!(subnet 192)
int e 1
ip address 192.1.10.66 255.255.255.240
!(subnet 64)
int s 0
ip address 172.16.65.2 (same subnet as router A's s 0)
!Int s 0 connects to router A
router rip
network 192.1.10.0
network 172.16.0.0
```

Host/Subnet Quantities Table

Class B # bits	Mask	Effective Subnets	Effective Hosts
1	255.255.128.0	2	32766
2	255.255.192.0	4	16382
3	255.255.224.0	8	8190
4	255.255.240.0	16	4094
5	255.255.248.0	32	2046
6	255.255.252.0	64	1022
7	255.255.254.0	128	510
8	255.255.255.0	256	254
9	255.255.255.128	512	126
10	255.255.255.192	1024	62
11	255.255.255.224	2048	30
12	255.255.255.240	4096	14
13	255.255.255.248	8192	6
14	255.255.255.252	16384	2

Class C # bits	Mask	Effective Subnets	Effective Hosts
1	255.255.255.128	2	126
2	255.255.255.192	4	62

3	255.255.255.224	8	30
4	255.255.255.240	16	14
5	255.255.255.248	32	6
6	255.255.255.252	64	2

*Subnet all zeroes and all ones included. These might not be supported on some legacy systems.

*Host all zeroes and all ones excluded.

NetPro Discussion Forums – Featured Conversations

Networking Professionals Connection is a forum for networking professionals to share questions, suggestions, and information about networking solutions, products, and technologies. The featured links are some of the most recent conversations available in this technology.

NetPro Discussion Forums – Featured Conversations for RP
Service Providers: MPLS
Virtual Private Networks: Services
Virtual Private Networks: Security

Related Information

- [IP Subnet Calculator \(registered customers only\)](#)
- [IP Routing Protocols Support Page](#)
- [Subnet Zero and the All-Ones Subnet](#)
- [Host and Subnet Quantities](#)
- [IP Subnet Calculation & Design Online Documentation](#)
- [Technical Support – Cisco Systems](#)

All contents are Copyright © 1992–2005 Cisco Systems, Inc. All rights reserved. Important Notices and Privacy Statement.

Updated: Sep 26, 2005

Document ID: 13788
